

## Configure Time Machine and Playback

SeaVision Playback provides the ability to view animated playback of historical vessel positions over a period between one hour and 30 days. Users are given the ability to scroll through selected time periods to view and analyze vessel data of the selected geographic area. SeaVision Playback data is available for up to one year prior to the current date, and can be used in conjunction with vessel filters, quick filters, and extended map filters.

- From the Navigation Bar, click Menu and then Map Tools. Enable Time Machine.
- Zoom in on the map to select Fetch Playback Data for this Area.
- Show history trails of the vessels displayed on the map.
- From the Playback tab, adjust the slider controls for a 6-hr. window. Use the blue scrubber bars along the timeline to adjust the playback time.
- From the Time Machine tab, take a snapshot of the current map.

## Configure Manual Report

**Manual Reports** allow you to report the location of a **vessel** or **incident** to display on the map. For both **vessels** and **incidents**, you must specify the date/time and position for the marker to be displayed on the map. On a **vessel** Manual Report, you can also specify **heading**, **course**, and **speed** and enable the marker to update as time progresses based on dead reckoning.

Manual Reports can be **shared** to a **Persona** or **Community**. Additionally, you can add **notes** to the manual report which may also be shared to a **Persona** or **Community**.

- From the Navigation Bar, click Menu and then Map Tools. Enable Manual Report.
- Create a Manual Report for a vessel. Place it on the map, then give it a name. It will be listed in Manual Reports Manager.
- Edit the Manual Report by clicking on the Report name. View Properties and zoom in on the marker.
- Edit the Properties and change the following:
  - Latitude and Longitude
  - Heading
  - Course Over Ground
  - Speed Over Ground
- Set Date/Time to 2 days and 7 hours earlier.
- Enable DR Position on a Manual Report by selecting the DR Position toggle.
- Adjust the map to see the DR Position for 2 days (48 hrs.). This is the DR Staleout Age.
- Change the DR Staleout Age to 1 day.
- Change the Speed Over Ground to 10 knots.
- Share the Report with Anyone in your Persona and Community.